



## HHR Reader installation on Windows 7 64-bit

To install the USB drivers you will need to do the following. First unzip the 'HHR Driver Repairing Tool.zip' file which came with these instructions. Remember where you unzip it as you will need the unzipped folder later in the installation process. Then plug the HHR reader into your computer and wait about a minute. Then from the 'Start menu' select 'Control Panel' and then the following:


Click on 'Hardware and Sound':




Click on 'Device Manager':




When Device Manger is displayed you should see you HHR reader attached as indicated below (please make sure it is powered on):




Right click on 'BioControl: Handheld reader' and select 'Update Driver Software...'




You will be then asked how to install the driver software. Please select 'Browse my computer for driver software'




You will then be asked where the software driver is located. Please select the location where you unzipped the driver software i.e. the 'HHR Driver Repairing Tool.zip' file. After that select 'Next'.



Briefly you will see an install window pop up followed by the following:




Now Device Manger window will show the following.







Please right click on 'USB serial port and select 'Update driver Software...'



Then please select 'Browse my computer for driver software':



Similar to the previous section, select the same location where you unzipped the 'HHR Driver Repairing Tool' and then select 'Next':



After a brief installing window appears the following should be displayed. This will complete your driver installation. You should now be able to use the Tags4all software to upload data from your reader.

